

ViKi Capture Server (0.1.0)

Download OpenAPI specification:

[Download](#)

cameras

List Devices

List all detected camera devices (RealSense and Kinect).

Returns

dict Keys: "realsense", "kinect", "active" (currently running), and error keys if any.

Responses

> **200** Successful Response

GET /api/devices

Response samples

200

Content type

application/json

[Copy](#)

```
null
```

Start Camera

Start streaming from a camera.

Parameters

`device_id` : str Camera identifier (serial for RealSense, "kinect_N" for Kinect). req : StartRequest FPS, resolution, depth mode, and Kinect sync options.

Returns

dict {"status": "started", "device_id": device_id}

Raises

HTTPException 500 If the backend fails to start.

PATH PARAMETERS

<code>device_id</code> required	string (Device Id)
---	--------------------

REQUEST BODY SCHEMA: `application/json`
required

<code>fps</code>	integer (Fps) Default: 15
<code>color_width</code>	integer (Color Width) Default: 1280
<code>color_height</code>	integer (Color Height) Default: 720

depth_mode	string (Depth Mode) Default: <code>"NFOV_UNBINNED"</code>
wired_sync_mode	integer (Wired Sync Mode) Default: <code>0</code>
subordinate_delay_us	integer (Subordinate Delay Us) Default: <code>0</code>
synchronized_images_only	boolean (Synchronized Images Only) Default: <code>false</code>

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/cameras/{device_id}/start

Request samples

Payload

Content type
application/json

Copy

```
{
  "fps": 15,
  "color_width": 1280,
  "color_height": 720,
  "depth_mode": "NFOV_UNBINNED",
  "wired_sync_mode": 0,
  "subordinate_delay_us": 0,
  "synchronized_images_only": false
}
```

```
}
```

Response samples

200**422****Content type**

application/json

[Copy](#)

null

Stop Camera

Stop streaming from a camera.

Parameters

`device_id` : str Camera ID.

Returns

`dict {"status": "stopped", "device_id": device_id}`

PATH PARAMETERS

<code>device_id</code> <code>required</code>	string (Device Id)
---	--------------------

Responses

> **200** Successful Response

> **422** Validation Error

POST `/api/cameras/{device_id}/stop`

Response samples

200

422

Content type
application/json

null

Copy

Camera Info

Get camera info (resolution, intrinsics, running status, latest frame timestamp).

Parameters

device_id : str Camera ID.

Returns

dict Camera info or 404 if not found/started.

PATH PARAMETERS

device_id required	string (Device Id)
-----------------------	--------------------

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/cameras/{device_id}/info

Response samples

200

422

Content type

application/json

null

[Copy](#)

Colour Stream

MJPEG stream of the colour image.

Parameters

`device_id` : str Camera ID. `undistort` : bool, default=True Apply undistortion using loaded intrinsics.

Returns

StreamingResponse Multipart MJPEG stream.

PATH PARAMETERS

<code>device_id</code> required	string (Device Id)
---	--------------------

QUERY PARAMETERS

<code>undistort</code>	boolean (Undistort) Default: true
------------------------	---

Responses

> **200** Successful Response

> **422** Validation Error

GET `/api/cameras/{device_id}/stream`

Response samples

200

422

Content type

application/json

[Copy](#)null

Depth Stream

MJPEG stream of the colour-mapped depth image.

Parameters

`device_id` : str Camera ID.

Returns

StreamingResponse Multipart MJPEG stream.

PATH PARAMETERS

`device_id`
required

string (Device Id)

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/cameras/{device_id}/depth

Response samples

200

422

Content type

application/json

null

[Copy](#)

calibration

Reset

Stop all calibration workers.

Returns

```
dict {"status": "success"}
```

Responses

> 200 Successful Response

POST /api/calibration/reset

Response samples

200

Content type

application/json

[Copy](#)

null

Sync

Synchronise board parameters across all calibration workers.

This updates the board size, square size, and (for ChArUco) marker size and dictionary for every active worker. Call this before starting calibration if the physical board changes.

Parameters

params : ArucoBoardParametersData or BoardParametersData Board parameters (fields depend on board_type). board_type : str "chess" or "aruco".

Returns

dict {"status": "success"}

Raises

HTTPException 422 If `aruco_dict` is invalid.

QUERY PARAMETERS

board_type
required

string (Board Type)

REQUEST BODY SCHEMA: application/json
required

Any of

ArucoBoardParametersData

BoardParametersData

board_size >
required

Array of items (Board Size) = 2 items

square_size required	number (Square Size)
marker_size required	number (Marker Size)
aruco_dict required	string (Aruco Dict)

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/calibration/sync

Request samples

Payload

Content type

application/json

Example

ArucoBoardParametersData

Copy Expand all Collapse all

```
{
  - "board_size": [
    0,
    0
  ],
  "square_size": 0,
  "marker_size": 0,
  "aruco_dict": "string"
}
```

Response samples

200**422****Content type**

application/json

[Copy](#)null

Capture

Manually capture a calibration sample for a specific camera.

The sample is added to the worker's internal collection if the board is detected.

Parameters

`device_id` : str Camera device ID.

Returns

dict Always returns {"status": "success"} – check worker status for actual sample count.

PATH PARAMETERS

<code>device_id</code> <i>required</i>	string (Device Id)
---	--------------------

Responses

> **200** Successful Response

> **422** Validation Error

POST `/api/calibration/capture/{device_id}`

Response samples

200

422

Content type

application/json

[Copy](#)

```
null
```

Capture All

Manually capture a calibration sample from all active workers.

Returns

```
dict {"status": "success"}
```

Raises

HTTPException 400 If no calibration workers are active (i.e., sync not called).

Responses

> **200** Successful Response

POST /api/calibration/capture

Response samples

200

Content type

application/json

Copy

null

Start Worker

Start a chessboard calibration worker for the given device.

Parameters

device_id : str Camera ID. mode : str, default="auto" "auto" for background capture thread, "manual" for explicit captures. params : BoardParametersData, optional Board size and square size; defaults to (8,6) and 0.025 m.

Returns

dict {"status": "success"}

PATH PARAMETERS

device_id	string (Device Id)
required	

QUERY PARAMETERS

mode	string (Mode)
	Default: auto

REQUEST BODY SCHEMA: application/json

Any of

BoardParametersData

Params

board_size >
required

Array of items (Board Size) = 2 items

square_size
required

number (Square Size)

Responses

> 200 Successful Response

> 422 Validation Error

POST /api/calibration/start/{device_id}

Request samples

Payload

Content type

application/json

Example

BoardParametersData

Copy

Expand all

Collapse all

```
{
  - "board_size": [
    0,
    0
  ],
  "square_size": 0
}
```

Response samples

200

422

Content type

application/json

Copy

null

Start Aruco Worker

Start a ChArUco board calibration worker for the given device.

Parameters

device_id : str Camera ID. mode : str, default="auto" "auto" or "manual". params :
ArucoBoardParametersData, optional Board parameters; defaults to (10,8) board, square 0.05 m,
marker 0.035 m, and DICT_5X5_100.

Returns

```
dict {"status": "success"}
```

Raises

HTTPException 422 If `aruco_dict` string is invalid.

PATH PARAMETERS

device_id	string (Device Id)
required	

QUERY PARAMETERS

mode	string (Mode)
	Default: <code>"auto"</code>

REQUEST BODY SCHEMA: application/json

Any of

- ArucoBoardParametersData
- Params

board_size > required	Array of items (Board Size) = 2 items
square_size required	number (Square Size)
marker_size required	number (Marker Size)
aruco_dict required	string (Aruco Dict)

Responses

> 200 Successful Response

> 422 Validation Error

POST /api/calibration/start/aruco/{device_id}

Request samples

Payload

Content type
application/json

Example
ArucoBoardParametersData

{

Copy Expand all Collapse all

```
- "board_size": [
  0,
  0
],
"square_size": 0,
"marker_size": 0,
"aruco_dict": "string"
}
```

Response samples

200

422

Content type

application/json

Copy

null

Status

Get calibration status for a device.

Parameters

device_id : str Camera ID.

Returns

dict {"samples_count": int, "started": bool}

PATH PARAMETERS

device_id
required

string (Device Id)

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/calibration/status/{device_id}

Response samples

200

422

Content type

application/json

Copy

null

Samples Count

Get the number of collected samples for a device.

Parameters

device_id : str Camera ID.

Returns

dict {"samples_count": int}

PATH PARAMETERS

device_id

required

string (Device Id)

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/calibration/samples_count/{device_id}

Response samples

200

422

Content type
application/json

null

Copy

Is Device Active

Check if a calibration worker is active for the device.

Parameters

device_id : str Camera ID.

Returns

dict {"is_device_active": bool}

PATH PARAMETERS

device_id required	string (Device Id)
-----------------------	--------------------

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/calibration/is_device_active/{device_id}

Response samples

200**422****Content type**

application/json

null

[Copy](#)

Clear

Clear all collected calibration samples for a device.

Parameters

device_id : str Camera ID.

Returns

```
dict {"status": "cleared"}
```

PATH PARAMETERS

<code>device_id</code> <code>required</code>	string (Device Id)
---	--------------------

Responses

> **200** Successful Response

> **422** Validation Error

POST `/api/calibration/clear/{device_id}`

Response samples

200

422

Content type

application/json

null

Copy

Intrinsics Post

Compute and save intrinsic parameters for a device (POST).

Uses the collected samples to run the calibration solve and persists the result to the default intrinsics file.

Parameters

device_id : str Camera ID.

Returns

IntrinsicsResponse Focal lengths, principal point, distortion coefficients.

Raises

RuntimeError If calibration fails (propagated as HTTP 500).

PATH PARAMETERS

device_id	string (Device Id)
required	

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/calibration/intrinsics/{device_id}

Response samples

200

422

Content type

application/json

Copy Expand all Collapse all

```
{
  "fx": 0,
```

```
    "fy": 0,  
    "cx": 0,  
    "cy": 0,  
  - "dist_coeffs": [  
    0  
  ]  
}
```

Intrinsics

Retrieve previously computed intrinsic parameters (GET).

Parameters

device_id : str Camera ID.

Returns

IntrinsicsResponse Focal lengths, principal point, distortion coefficients.

Raises

HTTPException 404 If intrinsics not found.

PATH PARAMETERS

device_id required	string (Device Id)
-----------------------	--------------------

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/calibration/intrinsics/{device_id}

Response samples

200

422

Content type

application/json

[Copy](#) [Expand all](#) [Collapse all](#)

```
{
  "fx": 0,
  "fy": 0,
  "cx": 0,
  "cy": 0,
  - "dist_coeffs": [
    0
  ]
}
```

Extrinsics Post All

Compute and save extrinsic parameters for all active devices.

Runs extrinsics calibration (pose estimation) using the most recent sample for each active device.

Returns

`list[ExtrinsicsResponse]` List of extrinsics (rvec, tvec) for each successfully calibrated device.

Raises

HTTPException 400 If no active cameras. HTTPException 422 If calibration fails for all devices (e.g., insufficient samples).

Responses

➤ **200 Successful Response**

POST /api/calibration/extrinsics

Response samples

200

Content type

application/json

Copy

Expand all

Collapse all

```
[
  - {
    "device_id": "string",
    + "rvec": [ ... ],
    + "tvec": [ ... ]
  }
]
```

Extrinsics

Retrieve previously computed extrinsic parameters (GET).

Parameters

device_id : str Camera ID.

Returns

ExtrinsicsResponse Rotation vector and translation vector.

Raises

HTTPException 404 If extrinsics not found.

PATH PARAMETERS

device_id
required

string (Device Id)

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/calibration/extrinsics/{device_id}

Response samples

200

422

Content type

application/json

Copy

Expand all

Collapse all

```
{
  "device_id": "string",
  - "rvec": [
    0
  ],
  - "tvec": [
    0
  ]
}
```

Extrinsics Viz

Return extrinsics, intrinsics and board info for the 3D skeleton panel.

Responses

> **200** Successful Response

GET /api/calibration/viz

Response samples

200

Content type

application/json

null

Copy

Marked Stream

MJPEG stream of the camera with calibration board overlay.

If a calibration worker exists, the stream shows detected markers/corners. Useful for checking board visibility during calibration.

Parameters

device_id : str Camera ID.

Returns

StreamingResponse Multipart MJPEG stream.

PATH PARAMETERS

device_id	string (Device Id)
required	

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/calibration/{device_id}/stream

Response samples

200**422****Content type**

application/json

null

[Copy](#)

skeleton

Toggle Estimation

Enable or disable skeleton estimation.

Parameters

req : ToggleRequest `enabled` boolean.

Returns

dict {"status": "updated", "enabled": bool}

REQUEST BODY SCHEMA: application/json
`required`

<code>enabled</code> <code>required</code>	boolean (Enabled)
---	-------------------

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/skeleton/toggle

Request samples

Payload

Content type
application/json

Copy

```
{
  "enabled": true
}
```

Response samples

200

422

Content type

application/json

null

[Copy](#)

Toggle Recording

Enable or disable recording of skeleton data to disk.

Parameters

req : ToggleRequest `enabled` boolean.

Returns

dict {"status": "updated", "recording": bool}

REQUEST BODY SCHEMA: application/json

`required`

`enabled`
`required`

boolean (Enabled)

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/skeleton/record

Request samples

Payload

Content type

application/json

Copy

```
{
  "enabled": true
}
```

Response samples

200

422

Content type

application/json

Copy

null

Get Status

Get current skeleton estimation and recording status.

Returns

dict {"enabled": bool, "recording": bool}

Responses

> 200 Successful Response

GET /api/skeleton/status

Response samples

200

Content type

application/json

null

Copy

List Recordings

List recorded skeleton data files (paginated).

Parameters

page : int, default=0 Page number. limit : int, default=10 Items per page.

Returns

dict {"recordings": list[str]} – list of filenames.

QUERY PARAMETERS

page	integer (Page)
	Default: 0

limit	integer (Limit)
	Default: 10

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/skeleton/recordings

Response samples

200

422

Content type

application/json

null

Copy

Smooth Recording

Apply Savitzky-Golay smoothing to a recorded skeleton file.

Parameters

req : SmoothRequest Filename, window length, and polynomial order.

Returns

dict {"status": "success", "path": str} – path to smoothed file.

Raises

HTTPException 404 If file not found. HTTPException 400 If smoothing parameters are invalid.
 HTTPException 500 If an internal error occurs.

REQUEST BODY SCHEMA: application/json
 required

filename required	string (Filename)
window_length	integer (Window Length) Default: 7
polyorder	integer (Polyorder) Default: 2

Responses

- > 200 Successful Response
- > 422 Validation Error

POST /api/skeleton/smooth

Request samples

Payload

Content type

application/json

[Copy](#)

```
{
  "filename": "string",
  "window_length": 7,
  "polyorder": 2
}
```

Response samples**200****422****Content type**

application/json

[Copy](#)

```
null
```

Smooth Plot

Return a PNG image comparing raw and smoothed wrist trajectories.

Parameters

filename : str Smoothed .npz file name.

Returns

Response PNG image.

Raises

HTTPException 404 If file not found.

QUERY PARAMETERS

filename	string (Filename)
required	

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/skeleton/smooth-plot

Response samples

200**422****Content type**

application/json

Copy

null

system

Get Config

Get the current user configuration (from `user_configuration.json`).

Returns

dict The configuration object.

Raises

HTTPException 404 If the user configuration file does not exist.

Responses

> **200** Successful Response

GET /api/config

Response samples

200

Content type

application/json

null

Copy

Save Config

Save a new configuration to `user_configuration.json`.

Parameters

config : dict Full configuration object.

Returns

dict {"status": "success"}

Raises

HTTPException 500 If saving fails (e.g., permission error).

REQUEST BODY SCHEMA: application/json
required

property name*
additional property any

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/config

Request samples

Payload

Content type
application/json

{ }

Copy

Response samples

200

422

Content type

application/json

Copy

null

Reset Config

Reset the user configuration to the default by copying `default_configuration.json`.

Returns

```
dict {"status": "success"}
```

Raises

HTTPException 404 If the default configuration file is missing. HTTPException 500 If copying fails.

Responses

> **200** Successful Response

POST `/api/config/reset`

Response samples

200**Content type**

application/json

[Copy](#)

```
null
```

Restart Server

Restart the server by exiting the process (container restarts automatically).

This endpoint calls `os._exit(1)`, which terminates the Python process. With Docker's `restart: unless-stopped`, the container will restart.

Responses

> **200** Successful Response

POST `/api/restart`

Response samples

200

Content type

application/json

[Copy](#)

```
null
```

recording

Start Recording

Start an RGB-D recording in the background worker.

The recording will run for the specified duration and save raw colour and depth data to the output directory.

Parameters

req : RecordRequest Duration (seconds), FPS, and output directory.

Returns

dict {"status": "recording started in background worker", "duration": float, "fps": int}

Raises

HTTPException 400 If no cameras are currently active.

REQUEST BODY SCHEMA: application/json

required

duration	number (Duration) Default: 10
fps	integer (Fps) Default: 15
output_dir	string (Output Dir) Default: "data/videos"

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/record/start

Request samples

Payload

Content type

application/json

Copy

```
{
  "duration": 10,
  "fps": 15,
  "output_dir": "data/videos"
}
```

Response samples

200

422

Content type

application/json

Copy

null

optimization

List Recordings

List available raw recordings (JSON files) that can be converted.

Returns

```
dict {"recordings": list[file_info]}
```

Responses

➤ **200** Successful Response

GET /api/optimization/recordings

Response samples

200

Content type

application/json

```
{ }
```

Copy

Convert Recording

Convert a raw JSON recording to a .npz sample suitable for retargeting.

Parameters

req : ConvertRequest Recording filename, output name, hand side, and arm inclusion.

Returns

dict Summary of the conversion: frames, fps, hand, orientation validity, etc.

Raises

HTTPException 400 If conversion fails.

REQUEST BODY SCHEMA: application/json

required

recording required	string (Recording)
output_name required	string (Output Name)
hand	string (Hand) Default: "right" Enum: "right" "left"
include_arm >	Include Arm (boolean) or Include Arm (null) (Include Arm)

Responses

> 200 Successful Response

> 422 Validation Error

POST /api/optimization/convert

Request samples

Payload

Content type

application/json

Copy

```
{
  "recording": "string",
  "output_name": "string",
  "hand": "right",
  "include_arm": true
}
```

Response samples

200

422

Content type

application/json

Copy

```
{ }
```

List Samples

List available smoothed skeleton samples (.npz files) for retargeting.

Returns

dict {"samples": list[file_info]}

Responses

> 200 Successful Response

GET /api/optimization/samples

Response samples

200

Content type

application/json

Copy

```
{ }
```

Retarget Endpoint

Enqueue a retargeting job.

Parameters

req : RetargetRequest Sample name, robot, output name, and optimisation parameters.

Returns

dict Job details (job_id, status, etc.).

Raises

HTTPException 404 If the sample file is not found.

REQUEST BODY SCHEMA: application/json

required

sample required	string (Sample)
robot	string (Robot) Default: ur10
output_name required	string (Output Name)
target_mode	string (Target Mode) Default: wrist_position Enum: wrist_position hand_se3
ik_position_cost >	Ik Position Cost (number) or Ik Position Cost (null) (Ik Position Cost)
ik_orientation_cost >	Ik Orientation Cost (number) or Ik Orientation Cost (null) (Ik Orientation Cost)
ik_solver >	Ik Solver (string) or Ik Solver (null) (Ik Solver)
joint_sg_window	integer (Joint Sg Window) Default: 0
sg_window	integer (Sg Window) Default: 0
recenter_to_neutral	boolean (Recenter To Neutral) Default: false
trajectory_scale >	Trajectory Scale (number) or Trajectory Scale (null) (Trajectory Scale)
trajectory_scale_origin	string (Trajectory Scale Origin) Default: auto Enum: auto initial_wrist robot_base
align_initial_orientation >	Align Initial Orientation (boolean) or Align Initial Orientation (null) (Align Initial Orientation)
evaluate	boolean (Evaluate) Default: true

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/optimization/retarget

Request samples

Payload

Content type

application/json

Copy

```
{
  "sample": "string",
  "robot": "ur10",
  "output_name": "string",
  "target_mode": "wrist_position",
  "ik_position_cost": 0,
  "ik_orientation_cost": 0,
  "ik_solver": "string",
  "joint_sg_window": 0,
  "sg_window": 0,
  "recenter_to_neutral": false,
  "trajectory_scale": 0,
  "trajectory_scale_origin": "auto",
  "align_initial_orientation": true,
  "evaluate": true
}
```

Response samples

200**422****Content type**

application/json

[Copy](#)

```
{ }
```

List Jobs

List all optimisation jobs (including finished and failed).

Returns

```
dict {"jobs": list[dict]}
```

Responses

> **200** Successful Response

GET /api/optimization/jobs

Response samples

200

Content type

application/json

Copy

```
{ }
```

Get Job

Get the status and details of a specific optimisation job.

Parameters

job_id : str Job ID.

Returns

dict Job details.

Raises

HTTPException 404 If job not found.

PATH PARAMETERS

job_id	string (Job Id)
required	

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/optimization/jobs/{job_id}

Response samples

200

422

Content type

application/json

Copy

{ }

List Outputs

List all generated output files (trajectories, evaluations).

Returns

dict {"outputs": list[file_info]}

Responses

> **200** Successful Response

GET /api/optimization/outputs

Response samples

200

Content type

application/json

Copy

{ }

Download Output

QUERY PARAMETERS

filename
required

string (Filename)

Responses

> 200 Successful Response

> 422 Validation Error

GET /api/optimization/outputs/download

Response samples

200

422

Content type

application/json

[Copy](#)null

Download Output By Filename

PATH PARAMETERS

filename
requiredstring (Filename)

Responses

[> 200 Successful Response](#)[> 422 Validation Error](#)

GET /api/optimization/outputs/{filename}

Response samples

200

422

Content type

application/json

null

Copy

dataset

List Smoothed Recordings

List smoothed skeleton recordings (cln-*.npz files) with pagination.

Parameters

page : int, default=0 Page number (zero-based). limit : int, default=10 Number of recordings per page.

Returns

dict {"recordings": list[str]} – list of filenames.

QUERY PARAMETERS

page

integer (Page)

Default:

`limit`

integer (Limit)

Default:

Responses

> **200** Successful Response

> **422** Validation Error

GET `/api/dataset/recordings`

Response samples

200**422****Content type**

application/json

[Copy](#)`null`

Optimize Recording

Start a background optimisation job for a smoothed recording.

Parameters

req : OptimizeRequest Filename (cln-*.npz) and robot name.

Returns

```
dict {"job_id": str, "status": "queued"}
```

Raises

HTTPException 404 If the recording file does not exist.

REQUEST BODY SCHEMA: application/json
required

filename required	string (Filename)
----------------------	-------------------

robot	string (Robot) Default: "ur10"
-------	-----------------------------------

Responses

> **200** Successful Response

> **422** Validation Error

POST /api/dataset/optimize

Request samples

Payload

Content type
application/json

Copy

```
{
  "filename": "string",
  "robot": "ur10"
}
```

Response samples

200

422

Content type

application/json

null

[Copy](#)

Optimize Status

Get the status of an optimisation job.

Parameters

`job_id` : str Job identifier returned by `/optimize`.

Returns

dict Job details.

Raises

HTTPException 404 If job not found.

PATH PARAMETERS

<code>job_id</code> <code>required</code>	string (Job Id)
--	-----------------

Responses

> **200** Successful Response

> 422 Validation Error

GET /api/dataset/optimize/status/{job_id}

Response samples

200

422

Content type

application/json

null

Copy

List Outputs

List all generated robot trajectory output files (.h5).

Returns

dict {"outputs": list[str]} – filenames.

Responses

> 200 Successful Response

GET /api/dataset/outputs

Response samples

200**Content type**

application/json

null

[Copy](#)

Retarget Debug Viz

Return the latest retargeting debug overlay as a PNG.

Responses

[> 200 Successful Response](#)

GET /api/dataset/debug-viz

Response samples

200**Content type**

application/json

null

[Copy](#)

Robot Viz Stream

MJPEG stream visualising a robot trajectory from an HDF5 file.

Parameters

filename : str Output filename (.h5). loop : bool, default=True Repeat the trajectory indefinitely.

Returns

StreamingResponse MJPEG stream of the 3D robot visualisation.

Raises

HTTPException 404 If the file does not exist.

QUERY PARAMETERS

filename <i>required</i>	string (Filename)
loop	boolean (Loop) Default: true

Responses

> **200** Successful Response

> **422** Validation Error

GET /api/dataset/viz-stream

Response samples

200**422****Content type**

application/json

null

[Copy](#)

List Optimize Jobs

List all optimisation jobs (history).

Returns

dict {"jobs": list[dict]} – each job details, sorted by creation time descending.

Responses

> **200** Successful Response

GET /api/dataset/optimize/jobs

Response samples

200

Content type

application/json

Copy

null

Index

Serve the main frontend HTML page.

Responses

> 200 Successful Response

GET /

